

# Getting Started with IVI Drivers

Your Guide to Using IVI with MATLAB®

Version 1.0

© Copyright IVI Foundation, 2009 All rights reserved The IVI Foundation has full copyright privileges of all versions of the IVI Getting Started Guide. For persons wishing to reference portions of the guide in their own written work, standard copyright protection and usage applies. This includes providing a reference to the guide within the written work. Likewise, it needs to be apparent what content was taken from the guide. A recommended method in which to do this is by using a different font in italics to signify the copyrighted material.

# **Contents**

Chapter 1	Introduction4
	Purpose
	Why Use an Instrument Driver?
	Why IVI?5
	Why Use an IVI Driver?
	Flavors of IVI Drivers
	Shared Components
	Download and Install IVI Drivers
	Familiarizing Yourself with the Driver
	Examples
Chapter 2	Using IVI with MATLAB®
	The Development Environment
	Example Requirements
	Download and Install the Driver
	Configure the IVI Driver
	Generate an Instrument Wrapper
	Configure and Control the Instrument
	Create an Instance of the Instrument15Connect to the Instrument15Configure the Instrument15Set the Trigger Delay16Set Reading Timeout16Display Reading16Disconnect from the Instrument16
	Remove the Driver from Memory
	- i di dioi illioittiddoll



# **Purpose**

Welcome to *Getting Started with IVI Drivers: Your Guide to Using IVI with MATLAB*®. This guide introduces key concepts about IVI drivers and shows you how to create a short program to perform a measurement. The guide is part of the IVI Foundation's series of guides, *Getting Started with IVI Drivers*.

Getting Started with IVI Drivers is intended for individuals who write and run programs to control test-and-measurement instruments. Each guide focuses on a different programming environment. As you develop test programs, you face decisions about how you communicate with the instruments. Some of your choices include Direct I/O, VXIplug&play drivers, or IVI drivers. If you are new to using IVI drivers or just want a quick refresher on the basics, Getting Started with IVI Drivers can help.

**Getting Started with IVI Drivers** shows that IVI drivers can be straightforward, easy-to-use tools. IVI drivers provide a number of advantages that can save time and money during development, while improving performance as well. Whether you are starting a new program or making improvements to an existing one, you should consider the use of IVI drivers to develop your test programs.

So consider this the "hello, instrument" guide for IVI drivers. If you recall, the "hello world" program, which originally appeared in *Programming in C: A Tutorial*, simply prints out "hello, world." The "hello, instrument" program performs a simple measurement on a simulated instrument and returns the result. We think you'll find that far more useful.

# Why Use an Instrument Driver?

To understand the benefits of IVI drivers, we need to start by defining instrument drivers in general and describing why they are useful. An instrument driver is a set of software routines that controls a programmable instrument. Each routine corresponds to a programmatic operation, such as configuring, writing to, reading from, and triggering the instrument. Instrument drivers simplify instrument control and reduce test program development time by eliminating the need to learn the programming protocol for each instrument.

Starting in the 1970s, programmers used device-dependent commands for computer control of instruments. But lack of standardization meant even two digital multimeters from the same manufacturer might not use the same commands. In the early 1990s a group of instrument manufacturers developed Standard

Commands for Programmable Instrumentation (SCPI). This defined set of commands for controlling instruments uses ASCII characters, providing some basic standardization and consistency to the commands used to control instruments. For example, when you want to measure a DC voltage, the standard SCPI command is "MEASURE: VOLTAGE: DC?".

In 1993, the VXI*plug&play* Systems Alliance created specifications for instrument drivers called VXI*plug&play* drivers. Unlike SCPI, VXI*plug&play* drivers do not specify how to control specific instruments; instead, they specify some common aspects of an instrument driver. By using a driver, you can access the instrument by calling a subroutine in your programming language instead of having to format and send an ASCII string as you do with SCPI. With ASCII, you have to create and send the instrument the syntax "MEASURE: VOLTAGE: DC?", then read back a string, and build it into a variable. With a driver you can merely call a function called MeasureDCVoltage() and pass it a variable to return the measured voltage.

Although you still need to be syntactically correct in your calls to the instrument driver, making calls to a subroutine in your programming language is less error prone. If you have been programming to instruments without a driver, then you are probably all too familiar with hunting around the programming guide to find the right SCPI command and exact syntax. You also have to deal with an I/O library to format and send the strings, and then build the response string into a variable.

# Why IVI?

The VXI*plug&play* drivers do not provide a common programming interface. That means programming a Keithley DMM using VXI*plug&play* still differs from programming an Agilent DMM. For example, the instrument driver interface for one may be ke2000\_read while another may be hp34401\_get or something even farther afield. Without consistency across instruments manufactured by different vendors, many programmers still spent a lot of time learning each individual driver.

To carry VXI*plug&play* drivers a step (or two) further, in 1998 a group of end users, instrument vendors, software vendors, system suppliers, and system integrators joined together to form a consortium called the Interchangeable Virtual Instruments (IVI) Foundation. If you look at the membership, it's clear that many of the foundation members are competitors. But all agreed on the need to promote specifications for programming test instruments that provide better performance, reduce the cost of program development and maintenance, and simplify interchangeability.

For example, for any IVI driver developed for a DMM, the measurement command is *IviDmmMeasurement.Read*, regardless of the vendor. Once you learn how to program the commands specified by IVI for the instrument class, you can use any vendor's instrument and not need to relearn the commands. Also commands that are common to all drivers, such as *Initialize* and *Close*, are identical regardless of

the type of instrument. This commonality lets you spend less time hunting around the help files and programming an instrument, leaving more time to get your job done.

That was the motivation behind the development of IVI drivers. The IVI specifications enable drivers with a consistent and high standard of quality, usability, and completeness. The specifications define an open driver architecture, a set of instrument classes, and shared software components. Together these provide consistency and ease of use, as well as the crucial elements needed for the advanced features IVI drivers support: instrument simulation, automatic range checking, state caching, and interchangeability.

The IVI Foundation has created IVI class specifications that define the capabilities for drivers for the following eight instrument classes:

Class	IVI Driver
Digital multimeter (DMM)	lviDmm
Oscilloscope	IviScope
Arbitrary waveform/function generator	lviFgen
DC power supply	IviDCPwr
Switch	lviSwtch
Power meter	IviPwrMeter
Spectrum analyzer	IviSpecAn
RF signal generator	IviRFSigGen

IVI Class Compliant drivers usually also include capability that is not part of the IVI Class. It is common for instruments that are part of a class to have numerous functions that are beyond the scope of the class definition. This may be because the capability is not common to all instruments of the class or because the instrument offers some control that is more refined than what the class defines.

IVI also defines custom drivers. Custom drivers are used for instruments that are not members of a class. For example, there is not a class definition for network analyzers, so a network analyzer driver must be a custom driver. Custom drivers provide the same consistency and benefits described below for an IVI driver, except interchangeability.

IVI drivers conform to and are documented according to the IVI specifications and usually display the standard IVI logo.



# Why Use an IVI Driver?

Why choose IVI drivers over other possibilities? Because IVI drivers can increase performance and flexibility for more intricate test applications. Here are a few of the benefits:

**Consistency** – IVI drivers all follow a common model of how to control the instrument. That saves you time when you need to use a new instrument.

**Ease of use** – IVI drivers feature enhanced ease of use in popular Application Development Environments (ADEs). The APIs provide fast, intuitive access to functions. IVI drivers use technology that naturally integrates in many different software environments.

**Quality** – IVI drivers focus on common commands, desirable options, and rigorous testing to ensure driver quality.

**Simulation** – IVI drivers allow code development and testing even when an instrument is unavailable. That reduces the need for scarce hardware resources and simplifies test of measurement applications. The example programs in this document use this feature.

**Range checking –** IVI drivers ensure the parameters you use are within appropriate ranges for an instrument.

**State caching –** IVI drivers keep track of an instrument's status so that I/O is only performed when necessary, preventing redundant configuration commands from being sent. This can significantly improve test system performance.

Interchangeability – IVI drivers enable exchange of instruments with minimal code changes, reducing the time and effort needed to integrate measurement devices into new or existing systems. The IVI class specifications provide syntactic interchangeability but may not provide behavioral interchangeability. In other words, the program may run on two different instruments but the results may not be the same due to differences in the way the instrument itself functions.

#### Flavors of IVI Drivers

To support all popular programming languages and development environments, IVI drivers provide either an IVI-C or an IVI-COM (Component Object Model) API. Driver developers may provide either or both interfaces, as well as wrapper interfaces optimized for specific development environments.

Although the functionality is the same, IVI-C drivers are optimized for use in ANSI C development environments; IVI-COM drivers are optimized for environments that support the Component Object Model (COM). IVI-C drivers extend the VXI*plug&play* driver specification and their usage is similar. IVI-COM drivers provide easy access to instrument functionality through methods and properties.

All IVI drivers communicate to the instrument through an I/O Library. Our examples use the Virtual Instrument Software Architecture (VISA), a widely used standard library for communicating with instruments from a personal computer.

# **Shared Components**

To make it easier for you to combine drivers and other software from various vendors, the IVI Foundation members have cooperated to provide common software components, called IVI Shared Components. These components provide services to drivers and driver clients that need to be common to all drivers. For instance, the IVI Configuration Server enables administration of system-wide configuration.

Important! You must install the IVI Shared Components before an IVI driver can be installed.

The IVI Shared Components can be downloaded from vendors' web sites as well as from the IVI Foundation Web site.

To download and install shared components from the IVI Foundation Web site:

- **1** Go to the IVI Foundation Web site at http://www.ivifoundation.org.
- 2 Locate Shared Components.
- 3 Choose the IVI Shared Components msi file for the Microsoft Windows Installer package or the IVI Shared Components exe for the executable installer.

#### **Download and Install IVI Drivers**

After you've installed Shared Components, you're ready to download and install an IVI driver. For most ADEs, the steps to download and install an IVI driver are identical. For the few that require a different process, the relevant **Getting Started** with IVI Drivers guide provides the information you need.

IVI Drivers are available from your hardware or software vendor's web site or by linking to them from the IVI Foundation web site.

To see the list of drivers registered with the IVI Foundation, go to <a href="http://www.ivifoundation.org">http://www.ivifoundation.org</a>.

# **Familiarizing Yourself with the Driver**

Although the examples in *Getting Started with IVI Drivers* use a DMM driver, you will likely employ a variety of IVI drivers to develop test programs. To jumpstart that task, you'll want to familiarize yourself quickly with drivers you haven't used before. Most ADEs provide a way to explore IVI drivers to learn their functionality. In each IVI guide, where applicable, we add a note explaining how to view the available functions. In addition, browsing an IVI driver's help file often proves an excellent way to learn its functionality.

# **Examples**

As we noted above, each guide in the *Getting Started with IVI Drivers* series shows you how to use an IVI driver to write and run a program that performs a simple measurement on a simulated instrument and returns the result. The examples demonstrate common steps using IVI drivers. Where practical, every example includes the steps listed below:

- Download and Install the IVI driver
   — covered in the Download and Install IVI
   Drivers section above.
- Determine the VISA address string Examples in Getting Started with IVI Drivers use the simulate mode, so we chose the address string GPIB0::23::INSTR, often shown as GPIB::23. If you need to determine the VISA address string for your instrument and the ADE does not provide it automatically, use an IO application, such as National Instruments Measurement and Automation Explorer (MAX) or Agilent Connection Expert.
- Reference the driver or load driver files For the examples in the IVI guides, the
  driver is the Agilent 34401A IVI-COM Specific Driver, Version 1.1.0.11,
   March 2006 (from Agilent Technologies) or the Agilent 34401A IVI-C
   Specific driver, Version 4.1, October 2006 (from National Instruments).
- Create an instance of the driver in ADEs that use COM For the examples in the IVI guides, the driver is the Agilent 34401A (IVI-COM) or HP 34401 (IVI-C).
- Write the program:
  - Initialize the instrument Initialize is required when using any IVI driver.
     Initialize establishes a communication link with the instrument and must be called before the program can do anything with the instrument. We set reset to true, ID query to false, and simulate to true.

Setting reset to true tells the driver to initially reset the instrument. Setting the ID query to false prevents the driver from verifying that the connected instrument is the one the driver was written for. Finally, setting simulate to true tells the driver that it should not attempt to connect to a physical instrument, but use a simulation of the instrument.

- Configure the instrument We set a range of 1.5 volts and a resolution of 0.001 volts (1 millivolt).
- Access an instrument property We set the trigger delay to 0.01 seconds.
- Set the reading timeout We set the reading timeout to 1000 milliseconds (1 second).
- Take a reading
- Close the instrument This step is required when using any IVI driver, unless the ADE explicitly does not require it. We close the session to free resources.

Important! Close may be the most commonly missed step when using an IVI driver. Failing to do this could mean that system resources are not freed up and your program may behave unexpectedly on subsequent executions.

- Check the driver for any errors.
- Display the reading.

**Note:** Examples that use a console application do not show the display.

Now that you understand the logic behind IVI drivers, let's see how to get started.



#### **The Development Environment**

MATLAB from The MathWorks is an interactive software environment for data acquisition and analysis, waveform generation, algorithm creation, and test system development. MATLAB also provides a technical computing language that is designed to help you solve technical challenges faster than with traditional software environments.

MATLAB supports IVI instrument drivers using the Instrument Control Toolbox. The toolbox provides additional MATLAB functionality.

#### **Example Requirements**

- MATLAB R2007a
- MATLAB Instrument Control Toolbox
- Agilent 34401A IVI-COM, Version 1.1.0.11, March 2006 (from Agilent Technologies)
- Agilent IO Libraries Suite 14.2

#### **Download and Install the Driver**

If you have not already installed the driver, go to the vendor Web site and follow the instructions to download and install it.


This example uses an IVI-COM driver, MATLAB also supports IVI-C drivers.

# Configure the IVI Driver

The Instrument Control Toolbox provides a graphical Test & Measurement Tool that enables you to interact with instrument drivers and instruments without writing MATLAB code. The Test & Measurement Tool lets you configure IVI driver properties in MATLAB and store them in the IVI configuration store.


- 1 At the MATLAB command line, type tmtool to launch the Test & Measurement Tool GUI. Or from the MATLAB Main Menu, select Toolboxes, then Instrument Control Toolbox and click Test & Measurement Tool. The Test & Measurement Tool GUI opens.
- 2 In the tree at left, click the IVI node under the Instrument Drivers node.

- **3** Select the *Hardware Assets* tab. In the Hardware Assets dialog, select Add and enter the following:
  - myDMM in the Name field
  - This is my Agilent 34401 Digital Multimeter in the Description field (optional)
  - GPIB0::23 in the IO Resource name field




- 4 Select the *Software Modules* tab. The installed IVI drivers appear.

  Note: If you have not installed the IVI driver, it will not appear in this list. You must close MATLAB, install the driver, and restart MATLAB for the driver to appear.
- 5 Select Agilent34401 from the drop-down list. The Software Modules dialog lists the module name, supported instrument models, and description.




Next, you must define your Driver Session to link the Software Module with the Hardware Asset and indicate whether you want to use Simulation Mode or other optional parameters when connecting.

- **6** Select the *Driver Sessions* tab. In the Driver Sessions dialog, select Add and enter the following:
  - DMM in the Name field
  - This session matches the Agilent 34401 driver with the hardware asset of GPIB0::23, and turns on Simulation mode of the driver in the Description field (optional)
- 7 Select Agilent34401 in the Software module drop-down list.
- 8 Select myDMM in the Hardware asset drop-down list.
- **9** Check Simulate in the options.



- **10** Select the *Logical Names* tab. In the Logical Names dialog, select Add and enter the following:
  - dmm in the Name field
  - This logical name enables your program to access any DMM independent of manufacturer or hardware asset in the Description field (optional)
  - **DMM** in the Driver session field



- **11** Select *File* and *Save IVI Configuration Store*. Saving to the store may take several moments.
- 12 Close the Test & Measurement Tool.

# **Generate an Instrument Wrapper**

We will now automatically generate an instrument driver wrapper file (.mdd) so that MATLAB can use the IVI driver.

At the MATLAB command prompt, type

```
makemid('dmm');
```

The file dmm. mdd appears in the current directory window. This is the instrument wrapper created by the makemid command. You may now use MATLAB to communicate with your instrument through an IVI driver.

**Note:** To help you learn the structure of a driver faster, MATLAB provides autocompletion support. As you are typing your commands for a driver, press the Tab key to get a selection of possible completions. You can also use the command "get" to see a list of possible properties and "methods" to get a list of methods on the object. "methodsview" will give you a graphical display of the methods also.

# **Configure and Control the Instrument**

You can interact with the instrument by using the Test & Measurement Tool or the MATLAB command line. We use the MATLAB command line here.

**Note:** All MATLAB methods and properties are available at the command line.

#### Create an Instance of the Instrument

To create an instance of the instrument, type

```
myDmm = icdevice('dmm');
```

#### Connect to the Instrument

Similar to the Initialize command in most ADEs, the Connect command in MATLAB initializes the instrument. The instrument will be initialized with the properties you specified using the Test & Measurement Tool. Type

```
connect (myDmm);
```

# **Configure the Instrument**

To set a range of 1.5 volts and resolution of 0.001 volts, type

```
myDmm.Range = 1.5;
myDmm.Resolution = 0.001;
```

#### **Set the Trigger Delay**

To set the trigger delay to 0.01 seconds, type

```
myDmm.Trigger.Delay = 0.01;
```

# **Set Reading Timeout**

To take a reading with a timeout of 1 second, type myDmm.Timeout = 0.01;

# **Display Reading**

To display the reading, type

```
data = invoke(myDmm.Measurement,'Read',1000)
```

#### **Disconnect from the Instrument**

Similar to the Close() command in most ADEs, the Disconnect command in MATLAB closes the instrument. To disconnect, type

```
disconnect (myDmm);
```

# **Remove the Driver from Memory**

To remove any reference to the driver from memory, type

```
delete(myDmm);
```

Your final application should contain the code below:

# **Further Information**

To learn more about using MATLAB with IVI instrument drivers, visit: <a href="http://www.mathworks.com/ivi">http://www.mathworks.com/ivi</a>

MATLAB is a registered trademark of The MathWorks, Inc.